

Tips & Tricks

Guide to Installing LinkOne Books Using LinkOne WinView Version 5

The purpose of this document is to assist users in installing LinkOne books onto their system from a CD / DVD ROM.

Prerequisites

LinkOne books can be installed onto a system from a CD / DVD ROM when the following prerequisites have been met:

1. LinkOne WinView is installed and licensed on the computer.
2. The CD / DVD ROM has the LinkOne books correctly installed prior to burning.

Instructions for the correct CD / DVD preparation process are available on our website:

<http://dstechwrite.com.au/> > Tips & Tricks > Delivering your Published LinkOne Books > 'Preparing, Packaging and Burning LinkOne Books to CD, DVD or Zip'.

Installing LinkOne Books from a CD / DVD ROM


LinkOne WinView requires specific files in the correct locations in order to locate and read LinkOne books.

These files are installed in the correct locations only when proper installation methods as detailed below are carried out.


NOTE: LinkOne books should not be installed by copying from the CD and pasting to a location.

Install LinkOne Books from the CD / DVD as follows:


1. Insert the CD / DVD into the DVD drive.
2. Open Ventyx LinkOne WinView Version 5.
3. In LinkOne WinView, go to Tools > Configuration.



4. Select Libraries from the left hand menu.




5. Select the Install Books icon located above the Libraries window.




- A 'Ventyx LinkOne Install Books Wizard' dialog opens (if the checkbox 'Don't show this welcome page again' has previously been selected, this window will not appear).




- Select Next
- Select File based library.
- Select the Browse button in Library location.



10. Navigate to the library folder on your CD or DVD (the library folder is the one above the OEM directory).




11. Select OK.
12. Click Next.
13. In the 'Choose The Books To Install' window, open the Publishers tree structure and select the LinkOne books to be installed.



14. Click Next.
15. In the 'Chose the Destination Library' window, select the library (local or network) where the books are to be installed, eg: C:\LinkOne.
16. Click Next.

17. An 'Installing The Books' window shows the status of the installation. Allow this process to complete.



18. Click Finish.
19. The LinkOne books have now been installed and can be accessed from the Browse Books dialog in LinkOne WinView (File > Open Book > Browse).