

Tips & Tricks

Installing the License into LinkOne Publisher (Version 5)

The purpose of this document is to assist users install the licence for LinkOne Publisher (Version 5).

Prerequisites

The license for LinkOne Publisher is obtained when the following prerequisites have been met:

1. The LinkOne Publisher software has been purchased.
2. The client has received access details for the ABB Customer Portal.
3. The client has downloaded the LinkOne Publisher software from the ABB Customer Portal.
4. The client has installed LinkOne Publisher onto the computer that is to build the production version of the LinkOne Books.
5. The installed LinkOne Publisher software has allocated a Machine Key.
6. The client has provided the Machine Key for the computer to DS TechWrite.
7. DS TechWrite has advised ABB of the client's Machine Key.
8. ABB has issued a LinkOne Publisher License for the client and forwarded it to DS TechWrite.
9. DS TechWrite has forwarded the LinkOne Publisher License to the Client.

For assistance, refer to <http://dstechwrite.com.au/> > Tips & Tricks > Getting Started with LinkOne for information on the following:

- Accessing the ABB Customer Portal,
- Downloading LinkOne software, and
- Finding the Machine Key required to create your Publisher Licence.

Installing the LinkOne Publisher License


NOTE: LinkOne Publisher and the supplied Publisher Licence may be installed on other computers if required for draft working purposes. These LinkOne Book Builder copies will produce draft books only. Only the machine with the registered Machine Key will be able to produce production books.

Install the Publisher license as follows:


1. Open LinkOne Book Builder as follows:

Go to: Start > All Programs > Ventyx LinkOne Publisher 5.? > Book Builder

- The following message will appear:



- Click OK.
- Go to Preferences > LinkOne Administration.




- Go to the Licenses Tab.
- Select New.
- Locate the email provided by DS TechWrite containing the Publisher license.
- The Publisher license is provided in the format shown below. The item highlighted (eg AAA-WA1-RLB-8A7-RQZ-LA9-VW1-LZP) is the Publisher license.

Publisher	5.0	16 May 2014	16 May 2015	CUSTOMER	14999	1	1000 pages/year	AAA-WA1-RLB-8A7-RQZ-LA9-VW1-LZP
-----------	-----	-------------	-------------	----------	-------	---	-----------------	---------------------------------

- Copy only the license number (eg AAA-WA1-RLB-8A7-RQZ-LA9-VW1-LZP).

10. Paste the license into the License entry box.



11. If an error message appears that the license is invalid, check that there are no extra spaces before or after the license number in the License entry box.

Graphic Filters

LinkOne Publisher has built-in graphic filters that ensure that the graphics are rendered correctly. These are listed under the Graphic Filters Tab.


There are at times requirements for specific filters for special graphics. These require licenses to be issued by ABB and inserted into the Licenses Tab before they will appear under the Graphic Filters Tab.

Should specific graphic filters be required, enquires should be addressed to DS TechWrite.

Once the graphic filter license has been received, install onto the computer as follows:

1. Open LinkOne Book Builder.
2. Go to Preferences > LinkOne.
3. Go to the Licenses Tab.
4. Select the New button.

5. Paste the provided graphic license into the License entry box.



DS TechWrite
.com.au